

DDS
What's new in 24.1.R0?



Visu-IT! GmbH April 3, 2024

© Copyright 2024 Visu-IT! GmbH An der Schergenbreite 1 93059 Regensburg



Table of Contents

1	DDS: Purpose and scope	. 3
2	DDS - What's new Info	. 3
2.1	Version 24.1.R0	3
2.1.1	New Features, Major Improvements	3
2.1.2	Minor Improvements, Correction of Bugs	3
3	DDS - What's new Appendix	. 4
3.1	No longer supported features	4
3.2	Questions?	4



1 DDS: Purpose and scope

This document describes the improvements and changes of the current DDS version compared to the previous versions.

2 DDS - What's new Info

2.1 Version 24.1.R0

2.1.1 New Features, Major Improvements

Key	What's New In Dds
ADDS-22269	ImpADD
	New Option "StructTypeMembersSortingStrategy" to control whether the structure-members of structures imported from ADD should be reordered according to the order rules used by ASCET. This option shall ensure that DDS and ASCET use the same memory layout for the declaration of shared structures in their header files after ExpSrc.
	The option can have one of the following values:
	 Default: Order of struct-members is kept as defined in ADD AccordingToAscet: Reorder struct members according to the ASCET algorithm
ADDS-21463	GenEdit: Update to Visual Studio 2022; it might be necessary to reboot your system after the initial installation.

2 issues

2.1.2 Minor Improvements, Correction of Bugs

Key	What's New In Dds
ADDS-22557	ImpCVX Fixed rare crash in ImpCVX with customer specific DDS DB and input cvs-file.

1 issue

Creation Date: April 3, 2024



3 DDS - What's new Appendix

3.1 No longer supported features

Key What's New In Dds

No issues found

3.2 Questions?

If you have any questions about this release, please contact the Visu-IT! Hotline:

DDS Hotline

Tel.: +49 941 - 49082-16 email: hotline@visu-it.com



DDS Product Page

Internet: visu-it.de/products/dds/

Creation Date: April 3, 2024